



# Ubuntu 16 Desktop **Client** Installation Guide

---



# Table of Contents

## [Ubuntu 16 Desktop Client](#)

### [1. Requirements](#)

#### [1.1 Hardware](#)

#### [1.1 Software](#)

### [2. Prerequisites / Dependencies](#)

### [3. Install](#)

### [4. Run](#)

### [4. Uninstall](#)

### [5. How to Troubleshoot](#)

# Ubuntu 16 Desktop Client

This guide provides all the prerequisite knowledge and steps to install invisily client on Ubuntu 16 Desktop (Linux) device.

## 1. Requirements

Hardware and software requirement to run invisily client are as below:

### 1.1 Hardware

- Processor: Minimum 2+ GHz Dual-core x86
- Memory (RAM): 4 GB

### 1.1 Software

- Supported Operating Systems:
  - Ubuntu 16.04 Desktop (64 bit)

## 2. Prerequisites / Dependencies

Ubuntu 16 Client installer/ package will install its dependencies automatically at the time of installation through their standard package manager.

## 3. Install

Download Ubuntu 16 Desktop (Linux) client installer from **Invisily Admin portal** ➔ **Software Management** ➔ **Software Updates** or request your IT admin to send you a download link through email.

1. The downloaded package will be in compressed format (e.g. ZIP). The user needs to extract the package (**invisily\_client.deb**) from the compressed file.
2. Open Terminal and assign permissions to debian installer/package "invisily\_client.deb" by running the following command in the terminal.

```
sudo chmod a+x invisily_client.deb
```

3. Install invisily client by running the following command in the terminal.

```
sudo apt-get install ./invisily_client.deb
```

4. In case of successful installation, the message "invisily-client installed successfully ..." will be displayed at the end of installation.

#### 4. Run

1. Open Applications Dashboard / Show Applications and search "invisily", invisily client shortcut will appear, click on it or you can find a shortcut of "invisily" on your Desktop click on it.
2. Enter credentials (username, password) and click on the login button.
3. On successful login, available/assigned services list will be displayed.

#### 4. Uninstall

1. Open Terminal and run the following command.

```
sudo apt-get remove invisily-client OR sudo apt-get purge invisily-client
```

#### 5. How to Troubleshoot

1. The debug and error log files are maintained at the installation path (/opt/invisily/linuxclient/client\_data/log/).