



Ubuntu Desktop **Client** Installation Guide



Table of Contents

[Windows Client](#)

[1. Requirements](#)

[1.1 Hardware](#)

[1.1 Software](#)

[2. Prerequisites / Dependencies](#)

[2.1. Driver Signing](#)

[2.1.1. Signing a Public Release of Driver](#)

[2.1.2. Signing during Development and Testing](#)

[2.2. Dot Net Framework](#)

[3. Install](#)

[4. Run](#)

[4. Uninstall](#)

Ubuntu Desktop Client

This guide provides all the prerequisite knowledge and steps to install invisily client on Ubuntu Desktop devices.

1. Requirements

Hardware and software requirement to run invisily client are as below:

1.1 Hardware

- Processor: Minimum 2+ GHz Dual-core x86
- Memory (RAM): 4 GB

1.2 Software

- Supported Operating Systems:
 - Ubuntu Desktop 18.x.x (64-bit)
 - Ubuntu Desktop 20.x.x (64-bit)

2. Prerequisites / Dependencies

Ubuntu Client installer/ package will install its dependencies automatically at the time of installation through their standard package manager.

3. Install

Download Ubuntu Desktop client installer from **Invisily Admin portal ➡ Software Management ➡ Software Updates** or request your IT admin to send you a download link through email.

3.1 Invisily Installation

1. The downloaded file will be in compressed format (e.g. ZIP). The user needs to extract the installer (**`invisily_client.deb`**) from the compressed file.
2. Open terminal and assign permissions to debian installer/package “invisily_client.deb” by running the following command in terminal:

```
sudo chmod a+x invisily_client.deb
```

3. Install invisily client by running the following command in terminal:

```
sudo apt-get install ./invisily_client.deb
```

4. If installation is successful, message “invisily-client installed successfully ...” will be displayed at the end of installation.

4. Run

1. Open Application Dashboard/Show Applications and search “invisily” - invisily client shortcut will appear. Click on it or you can find a shortcut of “invisily” on your desktop and click on it.
2. Enter credentials (username, password) and click on login button.
3. On successful login, available/assigned services list will be displayed.

4. Uninstall

1. Open terminal and run the following command:

```
sudo apt-get remove invisily-client
```

5. How to Troubleshoot

1. The debug and error log files are maintained at this path:

```
/opt/invisily/linuxclient/client_date/log
```